

# Refinitiv FXall AAA

## 8.0.X QUICK INSTALL GUIDE (CORPORATE EMAIL LOGIN)

### AUDIENCE - CORPORATE EMAIL LOGIN (AAA)

- **AAA Corporate email address login** - If you login to FXall using your corporate email address please use this install guide.
- **FXall user ID login (SiteMinder)** - If you login to FXall using your FXall user ID click [here](#) to download the *FXall SiteMinder 8.0.x Quick Install Guide (FXall Login ID)*.

### INTRODUCTION

This document describes a manual installation of Refinitiv FXall 8.0.x and any subsequent versions and patch releases of 8.0. If you need more information about the installation please refer to the [Refinitiv FXall AAA 8.0 Installation Guide](#).

---

**Warning:** It is mandatory that all clients are using version 7.7 or above.  
Any clients running a version below 7.7 may lose access to FXall at any time.

---

The latest FXall Release Notes are available on [MyRefinitiv FXall](#) in the **Support Materials** section.

By default, FXall is installed **alongside** previous versions of FXall. See [Download and extracting the software](#) below to start the installation process.

### DOWNLOAD AND EXTRACTING THE SOFTWARE


1. Ensure your system meets the minimum hardware, software and bandwidth requirements. See the [FXT Supported Environments](#) document for details.

2. Click [here](#) to go to the **My Refinitiv – Software Downloads page for Refinitiv FXall**

Two versions of FXall are available:

- 64-bit - **Refinitiv FXall Trading Desktop Application (Windows Version) – 8.0.0.nnn**
- 32-bit - **Refinitiv FXall Trading Desktop Application (Windows Version) - 8.0.0.nnn.32bit**

Users must ensure they download and install the appropriate version that matches their operating system.

3. Click the download button (  ) for the 64-bit or 32-bit version of **Refinitiv FXall Trading Desktop Application (Windows version) – 8.0.0.nnn** to start the process to download the setup zip file. The setup zip file is used to install FXall.
4. Right-click the downloaded zip file (RefinitivFXallApplication8.0.0.nnn-Windows-32bit.zip or RefinitivFXallApplication8.0.0.nnn-Windows.zip) and select **Extract All**. The **Extract Compressed (Zipped) Folders** dialog box is displayed.
5. Browse to the location where you want to extract the software to.
6. Click the **Extract** button.
7. Open the folder where the software was extracted to.
8. Double click **Refinitiv-FXall-Setup-64.exe** or **Refinitiv-FXall-Setup-32.exe**. The **InstallAnywhere** wizard is displayed and the install begins.

## INSTALLING FXALL

After you have double-clicked **Refinitiv-FXall-Setup-64.exe** or **Refinitiv-FXall-Setup-32.exe**, the **InstallAnywhere** wizard is displayed and then the **Introduction** dialog box is displayed.

### NOTE

The FXall Install program is now displayed in Refinitiv branding.

1. **Introduction** - click the **Next** button.
2. **End-User License Agreement** - Review and select the **I accept...** radio button.
3. Click the **Next** button.
4. **Choose Install Folder** - Select the software installation destination folder and click the **Next** button.
5. **User Data Folder** - Select the user data destination folder and click the **Next** button.
6. **Log File Folder** - Select the log file destination folder and click the **Next** button.
7. **Environment Selection** - Select the **Production** checkbox. This is the live trading environment. Only select **Integration** if access has been pre-arranged. Then click the **Next** button.
8. **Proxy Setup** - If a network **proxy** is used by this PC for connection to the Internet, enter the information in the appropriate fields.

### NOTE

Check with your local **network administrator** to determine whether a proxy server is used at your site.

The proxy information can be modified later using the **Refinitiv FXall Configuration Manager**. See the [Refinitiv FXall AAA 8.0 Installation Guide](#) for details.

9. Enter any relevant proxy specifications
10. Click the **Next** button.
11. **Choose Shortcut Folder** - At the bottom of the window select the **Create Icons for All Users** checkbox.
12. Select the appropriate radio button to indicate where the **shortcuts** to FXall are to appear. The default is to create an FXall shortcut in the program group called **Refinitiv FXall\_-8.0.0.nnn**.
  - If this is a new installation of FXall, or you have already uninstalled a previous version of FXall, you can accept the default location and click the **Next** button.
13. **Pre-Installation Summary** - Review the installation details.
14. Click the **Install** button.
15. **Installing Refinitiv FXall\_-** - When the installation finishes the **Install Complete** window appears. Then click the **Done** button. The installation is now complete. You can now launch Refinitiv FXall 8.0.x.

## DEFAULT PATH TO LAUNCH FXALL WHEN USING WINDOWS 8.1

**Start > All Programs > Refinitiv FXall\_-8.0.0.nnn > 8.0.0.nnn > Refinitiv FXall\_-** The **Login** window is displayed.

## DEFAULT PATH TO LAUNCH FXALL WHEN USING WINDOWS 10

**Start > All Programs > Refinitiv FXall\_-8.0.0.nnn > Refinitiv FXall\_-** The **Login** window is displayed.